

GEUTEBRÜCK

G-Health

Software Release Version 3.4.107

Feature List

G-Health 3.4.107

Software	Type	Short description	Details
Changes	G-Health	Important information!	Due to a change in the G-Health digital certificate subject, G-Health server v3.4.107 is unable to automatically upgrade clients prior to v3.4.104. Sites with older clients should install G-Health server v3.4.104 first, then wait for all clients to upgrade. The server can be upgraded to v3.4.107 once this has completed.
Bug fix	G-Health	Connection issues with v3.4.106	Fixed a bug where G-Health client's running v3.4.106 were unable to connect to G-Core servers due to a change in the digital certificate used by G-Health.
Security Issues	G-Health	CSV Injection	A potential issue was identified where a logged in user could change the name of a G-Health client in a way which could lead to CSV Injection if the client or alarm export function was used. This issue has now been fixed in G-Health.

Technical alterations reserved.

GEUTEBRÜCK GmbH

Im Nassen 7-9 | D-53578 Windhagen | Tel. +49 (0)2645 137-0 | Fax-999 | E-mail: info@geutebrueck.com | Web: www.geutebrueck.com