

GEUTEBRÜCK

G-Health

Software Release Version 3.5.123

Feature List

G-Health 3.5.123

Software	Type	Short description	Detailed description
Important Note	Client Updater		Due to a change in the G-Health digital certificate subject, G-Healthserver v3.5.123 is unable to automatically upgrade clients prior to v3.4.104. Sites with older clients should install G-Health server v3.4.104 first, then wait for all clients to upgrade. The server can be upgraded to v3.5.123 once this has completed. Otherwise clients must be manually upgraded.
Bug Fix	Web Console	Client Search	An issue was identified where a client search/filter would not work when a hyphen was in the client name
Bug Fix	Installer	Alarm Trigger Interval Change	Due to an error with the elasticsearch installer, when performing a fresh install of G-Health Server v3.5.122 there would be false alarms prepopulated in the system. This has been corrected.

Technical alterations reserved.

GEUTEBRÜCK GmbH

Im Nassen 7-9 | D-53578 Windhagen | Tel. +49 (0)2645 137-0 | Fax-999 | E-mail: info@geutebrueck.com | Web: www.geutebrueck.com